

Software Release Notes

dSS V1.19.6.1 and V1.19.2.1

digitalSTROM AG uses Software Release Notes (SRN) to provide information about software changes and updates of existing products.

Document number	SRN-2305
Date / Version	02.05.2023 / v3.1

Changes

- Fixed: Improved error reporting for overheating dSM11 devices.

Other

The current state of our various cloud services can be seen online at <http://status.digitalstrom.com>. If you notice any complications with any of the cloud-based services, please inform yourself on this page.

Software Update Recommendation

Updating to this software-version is recommended to benefit from the latest improvements and features.

Documentation

Further information about the features and how to use them can be found in the latest digitalSTROM manual under "Operation and Configuration" or "Installation".

The latest version of the manuals can be found on <https://www.digitalstrom.com/en/user-manuals/>

Affected Products

Product	Software Description	New Version	Release date
digitalSTROM-Server dSS20 / dSS22	dSS	1.19.6.1	05.06.2023
digitalSTROM-Server dSS11-1GB, dSSIP and dSS11E	dSS	1.19.2.1	05.06.2023
digitalSTROM-Meter dSM20 / dSM25 dSM12 (1.19.6.1)	dSM2x dSM1x	2.6.0 1.43.0	05.06.2023
digitalSTROM-Meter	dSM2x	2.5.1	05.06.2023

dSM20 / dSM25 dSM12 (1.19.2.1)	dSM1x	1.42	
-----------------------------------	-------	------	--

Installation Notes

dSS and dSM

- Execute the software update from the digitalSTROM configurator within the menu "*System / System Update*".
- The dSS must be connected to the Internet in order to perform the update. Alternatively, the update can be installed by using a USB thumb drive.
- It is advisable to back up your system settings prior to performing a system update within the menu "*System / System Maintenance*".
- Once the system updates are installed, the system checks again for available updates. In case there are additional dSM firmware updates available, they must be installed manually by clicking the "*Update System*" button.
- A complete list of release notes as well as the USB update file can be found at <http://www.digitalstrom.com/Partner/Support/Software-Updates/>.


dS Smart Home App

- The newest version of the **dS Smart Home App** is available online
 - iOS: Apple App Store
 - Android: Google Play Store

How to find the version information

dSS and dSM

The currently installed software version can be found within the digitalSTROM Configurator.



The screenshot shows the 'Hardware' tab in the digitalSTROM Configurator. It displays two sections: 'Meters & Controllers' and 'Devices'.

Meters & Controllers Table:

Status	Name	ID	Number of De...	Lock new Devi...	Pow...	Software Version	HW Version	HW Info
●	F1 Küche, Korridor	00003425	37	disabled	161	1.34.0.0 / DSP: 1.8.0.0	11.1.24.0	dSM11
●	F2 Bad, Wohnzimmer	00003e7d	36	disabled	50	1.34.0.0 / DSP: 1.8.0.0	12.1.1.0	dSM12

Devices Table:

Name	ID	Output Mode	Input Mode	Input	Status	Room Name	Ro...	HW Info	Firmw...	Register...	Inactive ...
Bankers Lam...	0000468c	dimmed	Device	Button 1		Korridor	3	GE-S...	3.5.5	-13 15:25:23	
Bankers Lam...	0000468d		Presets 0-4	Button 2		Korridor	3	SW-S...	3.5.5	-13 15:25:32	
Brandmelder...	0001f587		Smoke detector	standard	No smoke	Küche	13...	SW-A...	3.5.7	-11 16:34:15	
Deckenlicht ...	000226e1	dimmed	Device			Küche	13...	GE-K...	3.5.6	-11 16:34:20	
Deckenlicht ...	00025df7	dimmed	Device			Küche	13...	GE-K...	3.5.6	-21 11:14:06	

Additional annotations in the screenshot: A red box highlights the 'Software Version' column in the Meters & Controllers table. Another red box highlights the '1.14.0' value in the 'Name' column of the Devices table, with the text 'dSS-Version' written next to it.

dS Smart Home App

The currently installed version can be found in the menu "Settings / About".

